

# Esko Manual .Tiff File Acquire

## Overview:

AIT 3.1 can be setup to manually acquire Esko one-bit tiff files. The following three naming conventions are recognized.

1. cyan.tif
2. jobname\_c.tif
3. jobname\_cyan.tif

## Setup Procedure:

```

PSIK.INI - Notepad
File Edit Format View Help
ColorGroup=Loreal.txt
ColorGroupB=UserRecipes.txt
UseAITDonorMapping=0
MappingName=
SetupOnlyNode=4

[actiffbm]
Init Dir=C:\DATA\USERS\1437154\Projects\AIT\Test
Files\TIFF\Nike_ML.tiff\Random\
AgfaFiles=0
GenericFiles=1

[exnull]
Init Dir=c:\

[pengine]
Acquire Init Dir=c:\
Export Init Dir=c:\
SaveFilterIndex=4
AvailableMemoryPercentage=95
DefaultBMTileSize=262144
h_tile=21047
w_tile=14882
h_offset=0
w_offset=0
h_gap=312
    
```

1. Ensure AIT 3.1 is not running
2. Within the C:\WINNT folder, open **PSIK.ini** file
3. Within the [actiffbm], modify the “GenericFiles=1” value.

Note:

- GenericFiles=0 (Tiff file disabled)
- GenericFiles=1 (cyan.tif naming)
- GenericFiles=2 (jobname\_c.tif naming)
- \*GenericFiles=3 (jobname\_cyan.tif naming)

\*Type 3 naming convention can be automated. This automation will only work if all jobs that are sent to the hot folder have the same number of separations.

4. Launch AIT 3.1
5. Create a Template.txt file and save into the same folder as the 1 bit tiff files

If using the GenericFiles=3 configuration and setting up to run automatically, the Template.txt file needs to be set to the number of separations in all jobs entering the hotfolder.

To set the number of separations:


- Determine the number of separation
- Deselect the check box, under Sep# that is 1 number greater than the number of separations in the jobs

Example:

Number of separations = 9

Deselect the check box next to Sep# 10

6. File/Acquire/Tiff Bit-Map to select the 1 bit tiff files manually




# Manipulating Show Export Screen in Automatic mode

## Overview:

While in automatic mode, the export dialog box is grayed out, disabling any manual manipulation.

This procedure enables the operator to change Crop option, Recipe List, Donor Mapping, and Donor Laydown order during an automated workflow

## Setup Procedure:



```
PSIK.INI - Notepad
File Edit Format View Help
DG01,5,Orange DO01,5,Blue DB01,5
SystemStatus=0,1,1,Intermediate,0
MediaTableInitialized=1
RipId0=PCCW
PortNumber0=2345
ExtPassParams0=1
EnableAdvancedControls=1
LastEditGrp=PantoneRecipes.txt
LastRecipeUsed=blue
ColorGroup=Loreal.txt
ColorGroupB=UserRecipes.txt
UseAITDonorMapping=0
MappingName=
SetupOnlyMode=0
EnableAdvancedControlsDuringHotFolder=1

[actiffbm]
Init Dir=C:\DATA\USERS\1437154\Projects\AIT\Test
Files\TIFF\Mike_M_.tiff\Random1
AgfaFiles=0
GenericFiles=1

[exnull]
Init Dir=c:\

[pengine]
```

1. Within the C:\WINNT folder, open **PSIK.ini** file
2. Within the [exapproval], add the following:  
“EnableAdvancedControlsDuringHotFolder=1”.

### Note:

EnableAdvancedControlsDuringHotFolder=0

(presents the export dialog box as disabled)

EnableAdvancedControlsDuringHotFolder=1

(presents the export dialog box as enabled)

3. Re-acquire the job

It is not necessary to restart the AIT 3.1 application

Filename: AIT3.1 Addendum.doc  
Directory: C:\DATA\USERS\1437154\Projects\AIT\AIT 3.1  
Template: C:\Documents and Settings\1437154\Application  
Data\Microsoft\Templates\Normal.dot  
Title: Esko Manual  
Subject:  
Author: Kevin Gentz  
Keywords:  
Comments:  
Creation Date: 6/21/2007 9:19 AM  
Change Number: 3  
Last Saved On: 7/5/2007 2:29 PM  
Last Saved By: Kevin Gentz  
Total Editing Time: 91 Minutes  
Last Printed On: 7/5/2007 2:29 PM  
As of Last Complete Printing  
Number of Pages: 2  
Number of Words: 288 (approx.)  
Number of Characters: 1,643 (approx.)